

**DIRECTORATE OF DISTANCE & CONTINUING EDUCATIONS**

**MANONMANIAM SUNDARANAR UNIVERSITY**

**TIRUNELVELI – 627012**

**OPEN AND DISTANCE LEARNING(ODL) PROGRAMMES**

**(FOR THOSE WHO JOINED THE PROGRAMMES FROM THE ACADEMIC YEAR 2023 – 2024)**



**M.Sc. CHEMISTRY  
COURSE MATERIALS  
INSTRUMENTAL METHODS OF CHEMICAL  
ANALYSIS  
JSCH41**

**By**  
**S. NAGARAJAN**  
Assistant Professor  
Department of Chemistry  
Manonmaniam Sundaranar University  
Tirunelveli 627012

# UNIT-I

## QUALITATIVE AND QUANTITATIVE ASPECTS OF ANALYSIS

### Fundamental Concepts in Chemistry and Measurements

Accurate measurement is essential in science, particularly in chemistry, where the properties of substances are determined quantitatively. The International System of Units (SI Units) provides a standardized method for measuring physical quantities such as mass, volume, temperature, and concentration. The fundamental SI units include the meter (m) for length, kilogram (kg) for mass, second (s) for time, kelvin (K) for temperature, and mole (mol) for the amount of substance. These units ensure uniformity and precision in scientific research and industrial applications.

A crucial distinction in measurement is between mass and weight. Mass refers to the amount of matter in an object and remains constant regardless of location. It is measured in kilograms (kg). Weight, on the other hand, is the force exerted by gravity on an object and is measured in Newtons (N). Since weight depends on gravitational acceleration, it varies from place to place, such as on Earth, the Moon, or other celestial bodies. Mass is measured using a balance, while weight is determined using a spring scale.

The mole is a fundamental concept in chemistry, defined as the amount of substance containing  $6.022 \times 10^{23}$  entities (atoms, molecules, or ions). This number, known as Avogadro's constant, serves as a bridge between atomic-scale measurements and macroscopic quantities. In practical applications, smaller units like millimoles (mmol), which equal  $10^{-3}$  moles, are frequently used. Another related unit is milli equivalence (mEq), which is particularly important in medicine and pharmaceuticals, as it considers both the amount and charge of ions in a solution.

Various concentration units are used to express the amount of solute in a solution. Molality (m) is defined as the number of moles of solute per kilogram of solvent. It is temperature-independent and often used in colligative property calculations. Molarity (M) refers to the number of moles of solute per liter of solution and is widely used in laboratory preparations. Normality (N) expresses the number of gram-equivalents of solute per liter of solution and is essential in acid-base and redox titrations. Additionally, percentage concentrations are

expressed in terms of weight/weight (% w/w), weight/volume (% w/v), and volume/volume (% v/v), which describe the relative amounts of solute in different solution forms.

For trace substance analysis, scientists use parts per million (ppm) and parts per billion (ppb) to express extremely small concentrations. These units are commonly applied in environmental science to measure pollutants, heavy metals, and toxic substances in water, air, and soil. PPM represents one part of solute per million parts of solution, while PPB denotes one part per billion, making these units crucial in maintaining safety and regulatory standards.

Another significant aspect of chemical measurements is the density and specific gravity of liquids. Density ( $\rho$ ) is defined as mass per unit volume, usually expressed in  $\text{g/cm}^3$  or  $\text{kg/m}^3$ , and is a key property for identifying substances. It determines material properties, such as whether an object will float or sink in a liquid. Specific gravity (SG) is a dimensionless quantity that compares the density of a substance to that of water. Since water has a density of  $1 \text{ g/cm}^3$  at standard conditions, the specific gravity of a liquid indicates whether it is heavier or lighter than water. This property is widely used in industrial applications, including fuel analysis, pharmaceuticals, and food processing.

Understanding these fundamental concepts in chemistry is essential for conducting precise measurements, preparing accurate chemical solutions, and analyzing substances in both laboratory and industrial settings. By mastering these principles, scientists and engineers ensure consistency and reliability in their experimental and analytical work.

### **Stoichiometry Calculations**

Stoichiometry is a fundamental concept in chemistry that deals with the quantitative relationships between reactants and products in a chemical reaction. It is based on the law of conservation of mass, which states that matter is neither created nor destroyed in a chemical reaction. Using balanced chemical equations, stoichiometry helps determine the amounts of reactants needed or products formed in a reaction.

#### **The key principles of stoichiometric calculations include:**

- **Mole Ratios** – Derived from the coefficients of a balanced chemical equation to determine reactant and product relationships.
- **Limiting Reactant** – The reactant that is completely consumed in a reaction, determining the maximum amount of product formed.

- **Excess Reactant** – The reactant that remains after the reaction has completed.
- **Theoretical Yield** – The maximum amount of product that can be obtained from a given number of reactants.
- **Actual Yield and Percentage Yield** – The actual yield is the amount of product obtained experimentally, while the percentage yield is calculated as:

$$\text{Percentage Yield} = \left( \frac{\text{Actual Yield}}{\text{Theoretical Yield}} \right) \times 100$$

Stoichiometry is widely applied in chemical manufacturing, pharmaceuticals, environmental science, and food processing to optimize reactant use and minimize waste.

### **Sampling and Evaluation of Analytical Data**

Sampling is the process of collecting a representative portion of a material for analysis. Accurate sampling is crucial to ensure that the analytical results reflect the actual composition of the whole batch. Depending on the nature of the sample, different sampling techniques are used, such as random sampling, systematic sampling, composite sampling, and stratified sampling.

Once a sample is collected, the data obtained from analytical measurements must be evaluated for accuracy, precision, and reliability. This involves several statistical methods, including:

- **Accuracy** – The closeness of the measured value to the true value. It is assessed using methods such as standard reference materials and calibration curves.
- **Precision** – The reproducibility of measurements when repeated under identical conditions. It is often measured using standard deviation or relative standard deviation.
- **Errors in Analysis** – Errors in analytical data can arise due to instrument limitations, human errors, or environmental factors. They are classified as systematic errors (consistent deviations due to faulty equipment or methods) and random errors (unpredictable variations in measurements).
- **Significant Figures and Rounding Off** – Ensuring that numerical results are reported with appropriate precision to avoid misleading conclusions.
- **Data Validation** – Analytical results are validated by comparing them with standard values, replicating experiments, or using control samples.

Accurate sampling and analytical data evaluation are essential in scientific research, quality control, and regulatory compliance in industries such as pharmaceuticals, food safety, environmental monitoring, and forensic science. By applying proper stoichiometric principles and analytical techniques, chemists can ensure precise and reliable results, leading to improved decision-making and product quality.

## **Errors in Analytical Measurements**

Errors are an unavoidable part of any scientific measurement. They can arise from various sources, including instrumentation, human limitations, and environmental factors. Understanding the types of errors and methods to minimize them is crucial for ensuring accuracy and reliability in scientific and industrial applications.

### **Types of Errors**

Errors in measurements can be classified into three main categories:

1. **Systematic Errors** – These errors occur consistently in the same direction and can be identified and corrected. They result from flaws in experimental procedures, instruments, or human mistakes. Systematic errors include:
  - **Instrumental Errors** – Caused by faulty or uncalibrated instruments, such as a misaligned balance or incorrect sensor readings.
  - **Method Errors** – Arise from incorrect experimental techniques, improper chemical reactions, or sample contamination.
  - **Personal Errors** – Result from human mistakes like misreading instruments, improper handling, or calculation mistakes.
2. **Random Errors** – These errors are unpredictable and arise due to uncontrollable variations in measurement conditions. Unlike systematic errors, they do not follow a consistent pattern. Examples include slight fluctuations in temperature, variations in instrument sensitivity, or differences in human perception while taking readings. Random errors can be minimized by taking multiple measurements and calculating the average.
3. **Gross Errors** – These errors are severe mistakes that occur due to carelessness or negligence, such as recording wrong values, using the wrong reagent, or misinterpreting

results. These errors are often avoidable through careful experimental design and proper training.

### **Accuracy and Precision**

In scientific analysis, the quality of measurements is evaluated based on accuracy and precision:

- Accuracy refers to how close a measured value is to the true or accepted value. A high degree of accuracy means that the measurement is correct. It is usually improved by calibrating instruments and using standardized methods.
- Precision describes how reproducible and consistent repeated measurements are. Even if the measurements are not accurate, they may still be precise if they are close to each other. Precision is improved by minimizing fluctuations and ensuring consistency in techniques.

For example, if a balance consistently gives readings of 9.8 g for an object that truly weighs 10 g, the balance is precise but not accurate. If it gives different readings like 9.8 g, 10.1 g, and 10.2 g, it is neither accurate nor precise. A good measurement system should be both accurate and precise.

### **Minimization of Errors**

To reduce errors and enhance the quality of results, the following strategies are used:

- Proper Calibration of Instruments – Regularly calibrating instruments against known standards ensures accurate readings.
- Use of Standardized Methods – Following established protocols and procedures reduces method errors.
- Taking Multiple Measurements – Repeating experiments and calculating averages help minimize random errors.
- Eliminating Parallax Errors – When using measuring instruments like burettes and thermometers, taking readings at eye level prevents errors.
- Proper Training and Skill Development – Ensuring that analysts are well-trained reduces human-related errors.

- Environmental Control – Controlling factors like temperature, humidity, and vibrations helps stabilize measurements.
- Data Validation and Cross-Checking – Comparing results with reference standards or conducting duplicate analyses ensures reliability.

## **Significant Figures**

Significant figures (also known as significant digits) refer to the number of meaningful digits in a measurement that contribute to its accuracy. They indicate the precision of a measurement and help in properly representing numerical values in scientific calculations. The concept of significant figures is crucial in experimental sciences, particularly in chemistry, physics, and engineering, where precise measurements are essential.

### **Rules for Identifying Significant Figures**

1. All nonzero digits are significant.

Example: 123 has three significant figures.

2. Zeros between nonzero digits are significant.

Example: 10203 has five significant figures.

3. Leading zeros (zeros before the first nonzero digit) are not significant.

Example: 0.0056 has two significant figures.

4. Trailing zeros in a number with a decimal point are significant.

Example: 45.600 has five significant figures.

5. Trailing zeros in a whole number without a decimal point are not significant.

Example: 2500 has two significant figures, but 2500. has four because of the decimal point.

6. Exact numbers (such as those from counting objects) have an infinite number of significant figures.

Example: 12 apples (considered as an exact value).

## **Significant Figures in Mathematical Operations**

When performing calculations, the number of significant figures must be considered to maintain proper precision.

## Addition and Subtraction

- The answer should have the same number of decimal places as the measurement with the fewest decimal places.

Example: 12.34 (2 decimal places) + 3.2 (1 decimal place) = 15.5 (rounded to 1 decimal place).

## Multiplication and Division

- The result should have the same number of significant figures as the measurement with the fewest significant figures.

Example:

$$4.56 \text{ (3 sig. figs)} \times 2.1 \text{ (2 sig. figs)} = 9.6 \text{ (rounded to 2 sig. figs).}$$

## Importance of Significant Figures

- They ensure that calculated results do not imply more precision than the measurements allow.
- They help maintain consistency in scientific reporting and data analysis.
- They prevent misleading conclusions by controlling rounding errors.

## Methods of Expressing Precision

Precision refers to the reproducibility of a set of measurements. Several statistical methods are used to express precision, ensuring that scientific data is reliable and meaningful. Below are individual notes on various methods used to express precision.

### 1. Mean (Arithmetic Mean)

The mean is the average of a set of values and is calculated as:

$$\text{Mean}(\bar{x}) = \frac{\sum x_i}{n}$$

where:

$x_i$  represents individual values,

$n$  is the total number of values.



Importance:

- The mean provides a central value of the data set.
- It is used in most scientific and statistical analyses to summarize data.

## 2. Median

The median is the middle value in a data set when arranged in ascending or descending order.

- If the number of observations (n) is odd, the median is the middle value.
- If n is even, the median is the average of the two middle values.

Importance:

- The median is useful when data contains outliers, as it is not affected by extreme values.
- It gives a better central value for skewed data distributions.

## 3. Average Deviation

The average deviation measures the dispersion of data from the mean and is calculated as:

$$\text{Average Deviation} = \frac{\sum |x_i - \bar{x}|}{n}$$

where:

- $|x_i - \bar{x}|$  represents the absolute difference between each value and the mean.

Importance:

- It gives a simple measure of how much values deviate from the mean.
- It is useful when a straightforward measure of dispersion is needed.

## 4. Standard Deviation ( $\sigma$ or $s$ )

The standard deviation quantifies the amount of variation in a dataset. It is calculated as:

$$\sigma = \sqrt{\frac{\sum (x_i - \bar{x})^2}{n}}$$

For sample standard deviation:

$$s = \sqrt{\frac{\sum (x_i - \bar{x})^2}{n - 1}}$$

where  $n - 1$  is used in samples to account for the degree of freedom.

where  $n - 1$  is used in samples to account for the degree of freedom.

Importance:

- A smaller standard deviation indicates that values are close to the mean.
- A larger standard deviation shows greater variability.
- It is widely used in scientific experiments to assess precision.

## 5. Coefficient of Variation (CV%)

The coefficient of variation (CV) expresses standard deviation as a percentage of the mean:

$$CV\% = \left( \frac{\sigma}{\bar{x}} \right) \times 100$$

Importance:

- It is useful for comparing variability across different data sets, even if their units are different.
- A lower CV% indicates greater precision.

## 6. Confidence Limits

Confidence limits provide a range in which the true mean is expected to lie within a certain probability. They are given by:

$$\bar{x} \pm t \times \left( \frac{\sigma}{\sqrt{n}} \right)$$

where  $t$  is the  $t$ -value from statistical tables based on the confidence level (e.g., 95% confidence).

Importance:

- It helps estimate how well a sample mean represents the population mean.
- It is widely used in research to determine reliability.

#### 7. Q-Test (Dixon's Q-Test)

The Q-test is used to detect and eliminate outliers in a small data set. It is calculated as:

$$Q = \frac{|X_{\text{outlier}} - X_{\text{nearest}}|}{X_{\text{range}}}$$

where:

- $X_{\text{outlier}}$  is the suspected outlier,
- $X_{\text{nearest}}$  is the closest value to the outlier,
- $X_{\text{range}}$  is the total range of the data.

If the computed Q value is greater than the critical value from the Q-test table, the outlier can be rejected.

Importance:

- It helps in identifying and removing anomalous data points.
- It is useful for small sample sizes.

#### 8. F-Test (F-Ratio Test)

The F-test is used to compare the variances of two datasets to determine if they are significantly different. The formula is:

$$F = \frac{\sigma_1^2}{\sigma_2^2}$$

where  $\sigma_1^2$  and  $\sigma_2^2$  are the variances of two datasets (the larger variance is always placed in the numerator).

If the calculated F-value is greater than the critical F-value from the F-distribution table, the variances are significantly different.

Importance:

- It is widely used in hypothesis testing.
- It helps determine whether two methods or conditions provide significantly different results.

## 9. T-Test (Student's T-Test)

The t-test is used to compare the means of two datasets to determine if they are significantly different. It is given by:

$$t = \frac{\bar{x}_1 - \bar{x}_2}{\sqrt{\frac{s_1^2}{n_1} + \frac{s_2^2}{n_2}}}$$

where:

- $\bar{x}_1$  and  $\bar{x}_2$  are sample means,
- $S_1^2$  and  $S_2^2$  are sample variances,
- $n_1$  and  $n_2$  are the sample sizes.

A t-test can be paired (for related samples) or unpaired (for independent samples).

Importance:

- It is used in hypothesis testing to compare experimental results.
- It determines whether differences between two means are statistically significant.

## The Least Squares Method for Deriving Calibration Plots

The Least Squares Method is a statistical technique used to determine the best-fitting straight line for a set of experimental data points. It is commonly applied in calibration plots, where an analytical signal (such as absorbance, intensity, or concentration) is plotted against a known variable (such as concentration of a standard solution).

### Principle of the Least Squares Method

In many scientific experiments, data points do not fall exactly on a straight line due to experimental errors or variations. The least squares method minimizes the sum of the squares

of the vertical deviations between the observed data points and the fitted line. The equation of a straight line is:

$$y=mx+c$$

where:

- y is the dependent variable (measured response),
- x is the independent variable (known concentration),
- m is the slope of the line,
- c is the y-intercept (the value of y when x=0).

### Mathematical Formulation

For a set of experimental data points  $(x_1, y_1), (x_2, y_2), \dots, (x_n, y_n)$ , the best-fit straight line is determined by solving the following equations:

1. Slope (m) Calculation:

$$m = \frac{n \sum x_i y_i - \sum x_i \sum y_i}{n \sum x_i^2 - (\sum x_i)^2}$$

2. Y-Intercept (c) Calculation:

$$c = \frac{\sum y_i - m \sum x_i}{n}$$

where:

- n is the number of data points,
- $\sum x_i$  and  $\sum y_i$  are the sums of x-values and y-values, respectively,
- $\sum x_i y_i$  is the sum of the product of corresponding xxx and yyy values,
- $\sum x_i^2$  is the sum of squared xxx-values.

### Application in Calibration Plots

A calibration plot is a graphical representation used in quantitative analysis where the instrument response (y) is plotted against the known standard concentrations (x).

### **Steps to derive a calibration plot using the Least Squares Method:**

1. Prepare standard solutions of known concentrations.
2. Measure the response (such as absorbance in spectrophotometry or peak area in chromatography).
3. Plot the data points on a graph with concentration on the x-axis and instrument response on the y-axis.
4. Apply the Least Squares Method to determine the best-fit line.
5. Use the equation  $y=mx+c$  to determine unknown concentrations from measured responses.

### **Importance of the Least Squares Method in Calibration**

- Ensures the best possible linear relationship between measured response and concentration.
- Reduces error in predicting unknown sample concentrations.
- Provides a statistically reliable method for data analysis in analytical chemistry, physics, and engineering.

This method is widely used in spectrophotometry, chromatography, and other instrumental techniques for accurate quantitative analysis.

## **UNIT-II**

### **ATOMIC ABSORPTION SPECTROSCOPY**

#### **Atomic Absorption Spectroscopy (AAS)**

Atomic Absorption Spectroscopy (AAS) is a widely used analytical technique for determining the concentration of metals in various samples. It is based on the principle that free atoms in the ground state absorb light of a specific wavelength, which corresponds to the energy required for electronic transitions.

#### **Principle of Atomic Absorption Spectroscopy**

When light of a particular wavelength passes through a vaporized sample, atoms absorb some of the light. The amount of light absorbed is directly proportional to the concentration of the element in the sample. This follows Beer-Lambert's Law, which states:

$$A = \log \left( \frac{I_0}{I} \right) = \epsilon cl$$

where:

A = Absorbance,

$I_0$  = Intensity of incident light,

I = Intensity of transmitted light,

$\epsilon$  = Molar absorptivity,

c = Concentration of the analyte,

l = Path length of the sample.

## **Instrumentation of AAS**

Atomic Absorption Spectroscopy consists of several essential components:

### **1. Light Source (Hollow Cathode Lamp)**

- A hollow cathode lamp (HCL) emits light of a specific wavelength characteristic of the element to be analyzed.
- Some instruments use an electrodeless discharge lamp (EDL) for higher sensitivity.

### **2. Atomizer**

- Converts the sample into free atoms in the gaseous state.
- Two types of atomizers are commonly used:
  - Flame Atomizer: Uses air-acetylene or nitrous oxide-acetylene flame.
  - Graphite Furnace Atomizer (Electrothermal Atomization): Provides higher sensitivity by heating the sample in a small graphite tube.

### **3. Monochromator**

- Selects the specific wavelength absorbed by the analyte and removes unwanted wavelengths.

### **4. Detector (Photomultiplier Tube or Photodiode Array)**


- Measures the intensity of absorbed light and converts it into an electrical signal.

### **5. Data Processing System**

- Converts electrical signals into absorbance values and determines the concentration of the element using a calibration curve.



## Atomic absorption spectroscopy



Priyanshudycentre.com

### Applications of AAS

- Environmental Analysis: Detection of heavy metals like lead, cadmium, and arsenic in water and soil.
- Clinical and Pharmaceutical Analysis: Measurement of trace metals in biological samples like blood and urine.
- Food and Agriculture: Determination of essential minerals and toxic metals in food and beverages.
- Metallurgical Analysis: Analysis of metal alloys and ores.

### Advantages of AAS

- Highly sensitive and specific for metal analysis.
- Can detect metals at very low concentrations (ppm to ppb levels).
- Requires minimal sample preparation.

### Limitations of AAS

- Can only analyze metals and a few non-metals.
- Requires careful calibration and matrix matching.
- Interference from other elements can affect accuracy.

Atomic Absorption Spectroscopy remains a crucial technique for metal analysis in various scientific and industrial applications due to its accuracy, sensitivity, and reliability.

### **Choice of Source**

The light source in AAS should emit radiation at specific wavelengths corresponding to the element being analyzed. The commonly used sources include:

- Hollow Cathode Lamp (HCL):
  - Most commonly used light source in AAS.
  - Contains a cathode made of the element to be analyzed, ensuring characteristic line emission.
  - Provides narrow spectral lines, reducing interference.
- Electrodeless Discharge Lamp (EDL):
  - Used for elements that do not perform well with HCL (e.g., arsenic, selenium).
  - Provides higher intensity and longer lifespan than HCL.
  - Requires a radio-frequency or microwave power supply for excitation.

### **Monochromator**

The monochromator in AAS isolates the desired wavelength of radiation corresponding to the element being analyzed and removes unwanted wavelengths.

- Types of Monochromators:
  - Prism Monochromator: Uses dispersion through a prism to separate different wavelengths.
  - Grating Monochromator (preferred): Uses a diffraction grating to provide better resolution and precise wavelength selection.

### **Key Considerations in Choosing a Monochromator:**

- High resolution to separate spectral lines.
- Low stray light to prevent signal interference.
- Proper bandwidth to ensure sufficient energy reaches the detector.

## Choice of Detector

The detector in AAS converts light intensity into an electrical signal, which is then processed to determine the absorbance of the sample.

- Photomultiplier Tube (PMT) Detector (Most Common):
  - Highly sensitive to low light intensities.
  - Provides fast response time and accurate detection of weak signals.
- Photodiode Array (PDA) Detector:
  - Allows simultaneous detection of multiple wavelengths.
  - Less sensitive than PMT but useful for high-throughput analysis.
- Charge-Coupled Device (CCD) Detector:
  - High sensitivity and good for multi-element analysis.
  - Used in advanced spectrometers with array-based detection.

## Choice of Flame

The flame in AAS is responsible for atomizing the sample into free atoms, allowing them to absorb radiation from the source. The choice of flame depends on the element being analyzed and its ionization potential.

- Air-Acetylene Flame (Most Common):
  - Temperature: 2300–2500°C.
  - Suitable for most metals like copper, zinc, and iron.
  - Produces a stable and moderate-temperature flame.
- Nitrous Oxide-Acetylene Flame:
  - Temperature: 2600–2900°C.
  - Used for refractory elements like aluminum, titanium, and vanadium, which require a higher temperature for atomization.
  - Reduces chemical interference in some metal analyses.

- Hydrogen-Air Flame:
  - Lower temperature ( $\sim 2000^{\circ}\text{C}$ ).
  - Used for elements with high volatility like alkali metals (sodium, potassium).

## **Burner Designs**

The burner in AAS ensures proper mixing of fuel and oxidant, producing a uniform flame for consistent atomization. Different burner designs include:

### **Slot Burner (Most Common):**

Provides a long optical path for better signal detection.

Ensures laminar flame for stable operation.

Used in flame AAS for high sensitivity and minimal noise.

### **Total Consumption Burner:**

Simple design but produces turbulence in the flame.

Less efficient than slot burners.

### **Premix Burner (Laminar Flow Burner):**

Ensures homogeneous mixing of fuel and oxidant before combustion.

Reduces turbulence, providing a more stable flame.

## **Techniques of Atomization**

Atomization is the process of converting a sample into free atoms. This is achieved using different techniques:

### **(a) Flame Atomization (FAAS – Flame AAS)**

The most common method used in AAS.

The sample solution is nebulized into fine droplets and introduced into a flame.

The heat from the flame evaporates the solvent, leaving solid particles that decompose into free atoms.

Commonly used flames:

Air-acetylene ( $2300\text{--}2500^{\circ}\text{C}$ ) – Suitable for metals like Cu, Zn, Fe.

Nitrous oxide-acetylene ( $2600\text{--}2900^{\circ}\text{C}$ ) – Used for refractory metals like Al, Ti.

Advantages: Simple, rapid, and cost-effective.

Limitations: High detection limits, interference from flame composition.

### **(b) Electrothermal Atomization (ETAAS – Graphite Furnace AAS)**

Uses a graphite furnace instead of a flame for atomization.

The sample is deposited into a small graphite tube and heated in three steps:

1. Drying (100–150°C) – Removes solvent.
2. Ashing (400–1200°C) – Eliminates organic and volatile substances.
3. Atomization (1200–3000°C) – Converts elements into free atoms.

#### **Advantages:**

- Requires very small sample volumes.
- Higher sensitivity than flame AAS (ppb-level detection).

#### **Limitations:**

- Slower analysis time.
- More expensive instrumentation.

### **(c) Hydride Generation Atomization (HGAAS)**

Used for elements that form volatile hydrides (e.g., As, Sb, Se, Te, Bi).

The sample reacts with **sodium borohydride (NaBH<sub>4</sub>)** to generate volatile hydrides:



The hydride gas is transported to a heated quartz cell where atomization occurs.


#### **Advantages:**

- Extremely low detection limits.
- Reduces matrix interferences.

**Limitations:** Limited to hydride-forming elements.

### **(d) Cold Vapor Atomization (CVAAS)**

- Used exclusively for mercury (Hg) analysis.
- The sample is treated with a reducing agent (stannous chloride, SnCl<sub>2</sub>), which reduces Hg<sup>2+</sup> to elemental Hg (0):



The elemental mercury is volatilized and transported to a quartz absorption cell.

#### **Advantages:**

- High sensitivity (ppt-level detection).
- No need for high temperatures.

**Limitations:**

- Only applicable for mercury analysis.

**2. Techniques of Sample Introduction**

Proper sample introduction ensures efficient atomization and reproducibility in AAS. The main techniques include:

**(a) Pneumatic Nebulization**

- Most common method in flame AAS.
- A nebulizer converts the liquid sample into an aerosol, which is carried into the flame.

**Types of nebulizers:**

- Concentric nebulizer (most common).
- Cross-flow nebulizer (used for high-solids samples).

**Advantages:**

- Simple and widely used.

**Limitations:**

- Large sample volume required (~1–5 mL).

**(b) Electrothermal Sample Introduction**

- Used in graphite furnace AAS.
- A small amount of liquid (~1–50  $\mu\text{L}$ ) is placed inside the furnace for heating.

**Advantages:**

- Higher sensitivity.
- Requires minimal sample volume.

**Limitations:**

- More time-consuming than flame AAS.

**(c) Hydride Generation Sample Introduction**

- Used for hydride-forming elements (As, Sb, Se).
- The volatile hydrides are produced in a reaction vessel and carried to the atomizer.
- Advantages: Enhances sensitivity and reduces interferences.
- Limitations: Only applicable for specific elements.

**(d) Cold Vapor Sample Introduction**

- Used exclusively for mercury detection.
- The mercury vapor is directly introduced into the absorption cell.

- Advantages: Extremely high sensitivity for Hg detection.
- Limitations: Only applicable to mercury analysis.
- 

## **Methods of Background Correction in Atomic Absorption Spectroscopy (AAS)**

Background correction in Atomic Absorption Spectroscopy (AAS) is essential to eliminate unwanted absorption from molecular species, flame gases, and matrix effects, ensuring accurate measurement of the target element. Several techniques have been developed for effective background correction in AAS.

### **1. Deuterium Lamp Background Correction**

#### **Principle:**

Uses a deuterium ( $D_2$ ) lamp, which emits a broad spectrum of UV radiation. The  $D_2$  lamp and element-specific hollow cathode lamp (HCL) alternately illuminate the sample. The total absorption (analyte + background) is measured with HCL, and only background absorption is measured with  $D_2$ . The difference gives the corrected analyte signal.

#### **Advantages:**

- Effective for continuous background absorption from molecular species.
- Widely used in flame AAS.

#### **Limitations:**

- Ineffective for background absorption at wavelengths above 320 nm.
- Does not correct for structured background interferences (overlapping spectral lines).

### **2. Zeeman Effect Background Correction**

#### **Principle:**

- Based on the Zeeman Effect, which splits atomic spectral lines in the presence of a strong magnetic field.
- A strong electromagnet is applied to the sample in a graphite furnace.
- The atomic absorption signal is split into  $\pi$  (central) and  $\sigma$  (shifted) components.
- Only the  $\pi$  component is absorbed by the analyte, while the  $\sigma$  components represent background absorption.
- The difference between total and background absorption gives the analyte signal.

**Advantages:**

- Highly effective for graphite furnace AAS (GFAAS).
- Corrects for both continuous and structured background interferences.

**Limitations:**

- Requires expensive and complex instrumentation.
- Not suitable for flame AAS due to the need for a strong magnetic field.

**3. Smith-Hieftje Background Correction (Self-Reversal Method)****Principle:**

Uses a pulsed high-current mode in the hollow cathode lamp (HCL). At low current, the HCL emits narrow atomic lines (absorbed by the analyte). At high current, self-reversal broadens the spectral line, covering both analyte and background absorption. The difference between normal and broadened signals is used for background correction.

**Advantages:**

- Effective for structured background interferences.
- Works well for graphite furnace AAS.

**Limitations:**

- Less effective for strong molecular absorption.
- Not widely available in all spectrometers.

**4. Continuum Source Background Correction****Principle:**

Uses a continuous radiation source (e.g., Xenon arc lamp) instead of a hollow cathode lamp.

The entire wavelength spectrum is measured, and the analyte absorption is extracted from the background signal.

**Advantages:**

- Provides real-time background correction.
- Corrects both structured and continuous background absorption.



**Limitations:**

- Less commonly used due to complex optics.
- Requires high-resolution monochromators.

**Sources of Chemical Interferences and Their Methods of Removal**

In Atomic Absorption Spectroscopy (AAS), chemical interferences occur when unwanted chemical reactions affect the atomization of the analyte, leading to inaccurate results. One major source of interference is the formation of stable compounds such as oxides, sulfates, or phosphates, which do not dissociate easily in the flame. For example, calcium can form calcium phosphate ( $\text{CaPO}_4$ ) or calcium sulfate ( $\text{CaSO}_4$ ), reducing the availability of free calcium atoms for absorption measurement. Another interference arises from ionization effects, where elements like sodium (Na), potassium (K), and calcium (Ca) ionize at high temperatures, reducing the number of neutral atoms available for detection. Additionally, chemical reactions in the flame can produce unwanted molecular species, such as aluminum forming aluminum oxide ( $\text{Al}_2\text{O}_3$ ), which reduces the absorption signal. Matrix effects can also influence the results, where variations in viscosity, surface tension, or droplet formation impact the efficiency of sample introduction into the flame.

To minimize these interferences, several techniques are used. One effective method is the use of releasing agents, which bind with interfering species to free the analyte. For instance, lanthanum chloride ( $\text{LaCl}_3$ ) or strontium chloride ( $\text{SrCl}_2$ ) can prevent phosphate interference in calcium analysis. Another approach involves protective agents, which form volatile complexes with the analyte, preventing the formation of stable compounds; for example, EDTA (Ethylenediaminetetraacetic acid) protects metal ions from reacting with interfering substances. Ionization suppressors, such as potassium (K) or cesium (Cs), are also used to prevent the ionization of easily ionizable elements by providing excess electrons. Adjusting flame conditions is another strategy, where selecting a nitrous oxide-acetylene flame instead of an air-acetylene flame can help reduce the formation of stable oxides, particularly for elements like aluminum and titanium. Additionally, matrix matching and the standard addition method help correct for matrix effects by ensuring that the standard solutions and samples have similar compositions.

**Techniques for the Quantitative Estimation of Trace-Level Metal Ions in Water Samples**

The detection and quantification of trace-level metal ions in water samples are crucial for environmental monitoring, industrial quality control, and public health assessments. Since metal ions are often present in very low concentrations, highly sensitive and selective techniques are required for accurate estimation. Several analytical techniques are commonly used, each with its own advantages and limitations.

One of the most widely used techniques is Atomic Absorption Spectroscopy (AAS), which includes Flame AAS (FAAS) and Graphite Furnace AAS (GFAAS). FAAS is suitable for detecting metal ions at parts per million (ppm) levels, while GFAAS offers higher sensitivity and can detect metals at parts per billion (ppb) levels. AAS is highly selective and widely used for metals such as lead (Pb), cadmium (Cd), and arsenic (As).

Another powerful technique is Inductively Coupled Plasma Optical Emission Spectroscopy (ICP-OES). This method uses a high-temperature plasma source to excite metal atoms, and the emitted light is measured to determine the concentration of metal ions. ICP-OES is capable of detecting multiple elements simultaneously with high precision and sensitivity. For even lower detection limits, Inductively Coupled Plasma Mass Spectrometry (ICP-MS) is employed. ICP-MS provides extremely high sensitivity, allowing trace metals to be detected at parts per trillion (ppt) levels, making it ideal for environmental and toxicological studies.

Electrochemical methods such as Anodic Stripping Voltammetry (ASV) and Differential Pulse Voltammetry (DPV) are also used for trace metal analysis. These methods involve the pre-concentration of metal ions on an electrode surface, followed by electrochemical stripping, which provides high sensitivity and low detection limits. ASV is particularly effective for heavy metals like lead, mercury, and copper.

X-ray Fluorescence Spectroscopy (XRF) is a non-destructive technique used for the rapid detection of metals in water. Although it is less sensitive than ICP-MS and AAS, it is useful for on-site analysis and screening applications.

For organic metal complexes, High-Performance Liquid Chromatography (HPLC) coupled with Mass Spectrometry (MS) is used to separate and quantify metal ions in complex samples. Similarly, Spectrophotometric Methods, involving colorimetric reactions with specific metal-chelating agents, provide a cost-effective approach for detecting trace metals, though they generally have higher detection limits.

Each technique has its own strengths, and the choice of method depends on factors such as the required sensitivity, the number of metal ions to be analyzed, sample complexity, and available instrumentation. By selecting the appropriate technique, accurate and reliable quantification of trace metals in water samples can be achieved, ensuring environmental safety and regulatory compliance.

## UNIT-III


### UV-Visible and IR Spectroscopy

#### Origin of Spectra:

Spectroscopy is the study of the interaction between electromagnetic radiation and matter. The origin of spectra in **UV-Visible (Ultraviolet-Visible) Spectroscopy** and **Infrared (IR) Spectroscopy** is based on the absorption of light by molecules, leading to electronic or vibrational transitions.

#### UV-Visible Spectroscopy

### Ultraviolet-Visible Spectroscopy



UV-Visible spectroscopy is based on the absorption of **ultraviolet (200-400 nm) and visible (400-800 nm) light** by molecules, causing electronic transitions. When a molecule absorbs UV or visible radiation, electrons in lower-energy molecular orbitals are excited to higher-energy molecular orbitals. The most common electronic transitions occur in molecules containing conjugated double bonds or non-bonding electrons. These include:

- $\pi \rightarrow \pi^*$  transitions (involving conjugated double bonds)
- $n \rightarrow \pi^*$  transitions (involving lone pair electrons in heteroatoms such as O, N, or S)
- $\sigma \rightarrow \sigma^*$  transitions (requiring high-energy UV radiation, usually below 200 nm)

The absorption spectrum in UV-Visible spectroscopy provides information about the structure of molecules, including conjugation and functional groups. The position and intensity of absorption bands depend on factors such as solvent polarity and molecular environment.

## IR Spectroscopy

Infrared spectroscopy deals with the absorption of **infrared radiation (4000-400 cm<sup>-1</sup>)**, which causes **vibrational transitions** in molecules. Unlike UV-Visible spectroscopy, which involves electronic transitions, IR spectroscopy focuses on the vibration of chemical bonds. Molecules absorb infrared radiation when the frequency of the IR light matches the natural vibrational frequency of the bonds, leading to a change in the **dipole moment** of the molecule.

The main types of molecular vibrations include:

- **Stretching vibrations**, where bond lengths change (e.g., C=O, O-H, N-H stretches)
- **Bending vibrations**, where bond angles change (e.g., scissoring, rocking, wagging, twisting)

Each functional group in a molecule absorbs IR radiation at a characteristic frequency, allowing IR spectroscopy to be used for functional group identification and structural analysis. The IR spectrum of a compound provides a "fingerprint" region (below 1500 cm<sup>-1</sup>) that is unique to each molecule.

## Interaction of Radiation with Matter: UV-Visible and IR Spectroscopy

When electromagnetic radiation interacts with matter, different types of transitions occur depending on the energy of the radiation. UV-Visible Spectroscopy and Infrared (IR)

Spectroscopy involve different regions of the electromagnetic spectrum and correspond to distinct types of molecular transitions.

### UV-Visible Spectroscopy: Electronic Transitions


UV-Visible spectroscopy involves the absorption of ultraviolet (200-400 nm) and visible (400-800 nm) light, leading to electronic transitions in molecules. When UV-Visible light interacts with a molecule, it provides sufficient energy to excite electrons from lower-energy molecular orbitals to higher-energy orbitals. The main types of electronic transitions include:

- $\pi \rightarrow \pi^*$  transitions (common in molecules with conjugated double bonds)
- $n \rightarrow \pi^*$  transitions (in molecules with lone pairs on heteroatoms like oxygen, nitrogen, or sulfur)
- $\sigma \rightarrow \sigma^*$  transitions (require higher energy and usually occur in the far-UV region)

The extent of absorption depends on the molecular structure, solvent effects, and conjugation. The absorption spectrum provides valuable information about electronic configurations, chromophores, and molecular interactions.

### IR Spectroscopy: Vibrational Transitions

#### IR Spectroscopy Instrumentation



Infrared spectroscopy involves the absorption of infrared radiation ( $4000\text{--}400\text{ cm}^{-1}$ ), which induces vibrational transitions in molecular bonds. Unlike UV-Visible spectroscopy, which excites electrons, IR radiation causes bonds to stretch and bend. For a molecule to absorb IR radiation, the vibration must lead to a change in dipole moment. The main types of vibrational transitions include:

- Stretching vibrations (changes in bond length, e.g., C=O, O-H, and N-H stretching)
- Bending vibrations (changes in bond angle, e.g., scissoring, rocking, wagging, and twisting)

Different functional groups absorb IR radiation at characteristic frequencies, creating an IR spectrum that acts as a molecular fingerprint. The intensity and position of absorption peaks depend on factors such as bond strength, atomic mass, and molecular environment.

## **Fundamental Laws of Spectroscopy and Selection Rules**

### **Fundamental Laws of Spectroscopy**

Spectroscopy is based on the interaction of electromagnetic radiation with matter, governed by fundamental laws that describe how radiation is absorbed, emitted, or scattered.

#### **Beer-Lambert Law**

- This law relates the absorption of light to the concentration of the absorbing species in a solution.
- **Mathematical expression:**

$$A = \epsilon cl$$

where,

A = Absorbance

$\epsilon$  = Molar absorptivity ( $\text{L mol}^{-1} \text{cm}^{-1}$ )

c = Concentration of the absorbing species ( $\text{mol L}^{-1}$ )

l = Path length of the sample (cm)

This law is the foundation of quantitative analysis in UV-Visible spectroscopy.

#### **Planck's Law**

Describes the energy of electromagnetic radiation in terms of discrete packets called quanta or photons.

##### **Formula:**

$$E = h\nu$$

where,

E = Energy of a photon

h = Planck's constant ( $6.626 \times 10^{-34} \text{ J}\cdot\text{s}$ )

$\nu$  = Frequency of radiation

This principle explains why molecules absorb radiation at specific frequencies.

#### **Bohr's Frequency Condition**

States that radiation is absorbed or emitted when a molecule undergoes a transition between two energy levels.

##### **Formula:**

$$\Delta E = h\nu$$

This explains the quantized nature of energy absorption and emission in spectroscopic techniques.

## Einstein's Law of Spontaneous and Stimulated Emission

Describes the probability of emission of photons from an excited state. **Spontaneous emission** occurs naturally without external influence, while **stimulated emission** occurs when an incoming photon triggers emission, which is the principle behind lasers.

## Selection Rules in Spectroscopy

Selection rules determine whether a particular transition is allowed or forbidden based on quantum mechanical principles. Different spectroscopic techniques follow specific selection rules.

### Electronic Spectroscopy (UV-Visible) Selection Rules

**Laporte Rule:** In centrosymmetric molecules, transitions within the same symmetry class (e.g.,  $g \rightarrow g$  or  $u \rightarrow u$ ) are forbidden. However, in asymmetric molecules, these transitions may occur.

**Spin Selection Rule:** Transitions between states of different spin quantum numbers are forbidden (e.g., singlet  $\rightarrow$  triplet transitions). However, spin-orbit coupling can relax this rule, leading to weak absorption bands.

### Vibrational Spectroscopy (IR and Raman) Selection Rules

**IR Selection Rule:** A vibration is IR-active if it causes a change in the **dipole moment** of the molecule.

**Raman Selection Rule:** A vibration is Raman-active if it causes a change in the **polarizability** of the molecule.

**Mutual Exclusion Principle:** In centrosymmetric molecules, vibrations that are IR-active are Raman-inactive and vice versa.

### Rotational Spectroscopy Selection Rules

A molecule must have a **permanent dipole moment** to exhibit a pure rotational spectrum in the microwave region.

The allowed transitions follow the rule:

$$\Delta J = \pm 1$$

where  $J$  is the rotational quantum number.

### validity of Beer-Lambert's law

The validity of Beer-Lambert's law depends on several conditions being met for accurate absorbance measurements. This law states that absorbance ( $A$ ) is directly proportional to the concentration ( $C$ ) of the absorbing species and the path length ( $L$ ) of the sample, given by the equation  $A = \epsilon CL$ , where  $\epsilon$  is the molar absorptivity. However, deviations from Beer-Lambert's law can occur due to instrumental, chemical, and physical factors.

Factors Affecting the Validity of Beer-Lambert's Law:

1. **Concentration Limitations:** At very high concentrations, molecular interactions such as aggregation, scattering, or changes in refractive index can cause deviations.
2. **Chemical Interactions:** Changes in pH, complex formation, or dissociation of the absorbing species can alter the absorbance behavior.
3. **Monochromatic Light Requirement:** The law is valid only if the incident light is monochromatic and the absorption remains constant across the wavelength range used.
4. **Stray Light and Instrumental Errors:** Imperfections in the spectrophotometer, such as scattered light, detector noise, and improper calibration, can lead to inaccuracies.
5. **Homogeneous Sample Distribution:** The absorbing species must be evenly distributed in the solution to avoid errors caused by non-uniformity in concentration.

## **UV-Visible Spectrometry**

### **Principle**

UV-Visible spectrometry is based on the principle of electronic transitions that occur when molecules absorb ultraviolet (UV) or visible light. When a beam of light passes through a sample, certain wavelengths are absorbed while others are transmitted. The amount of absorbed light is measured and used to determine the concentration of the absorbing species in the sample.

This technique follows Beer-Lambert's law, which states that absorbance ( $A$ ) is directly proportional to the concentration ( $C$ ) of the absorbing species and the path length ( $L$ ) of the sample:

$$A = \epsilon CL$$

where  $\epsilon$  is the molar absorptivity, a constant specific to each substance. The absorption of UV or visible light excites electrons from a lower energy state (ground state) to a higher energy state (excited state). The energy absorbed corresponds to the difference between these electronic energy levels. Different functional groups in molecules absorb at characteristic wavelengths, making UV-Visible spectrometry a valuable tool for identifying compounds, determining concentrations, and studying molecular interactions.

### **Instrumentation of UV-Visible Spectrophotometry**

The instrumentation of a UV-Visible spectrophotometer consists of key components such as a light source, monochromator, sample holder, detector, and signal processor. The design may vary between single-beam and double-beam spectrophotometers, each with specific advantages in analytical applications.



### 1. Choice of Light Source:

The light source should provide a stable and continuous emission across the UV (200–400 nm) and visible (400–800 nm) ranges. Common sources include:

- Deuterium Lamp – Emits in the UV region (160–400 nm).
- Tungsten-Halogen Lamp – Covers the visible and near-infrared region (320–2500 nm).
- Xenon Arc Lamp – Provides a broader spectral range and high-intensity output.

### 2. Monochromator:

The monochromator selects a specific wavelength from the light source and directs it toward the sample. It consists of:

- Entrance slit – Controls the amount of light entering the system.
- Dispersion element (Prism or Diffraction Grating) – Separates light into its component wavelengths.
- Exit slit – Selects the desired wavelength to pass through the sample.

Diffraction gratings are commonly used due to their ability to provide high-resolution wavelength selection with minimal stray light interference.

### 3. Detector:

Detectors convert transmitted light into an electrical signal, which is then processed to determine absorbance. Common detectors include:

- Photomultiplier Tubes (PMT) – Highly sensitive, ideal for detecting low light intensities.
- Silicon Photodiodes – More stable and compact, commonly used in modern instruments.
- Charge-Coupled Devices (CCD) – Enable multi-wavelength detection simultaneously.

### 4. Single-Beam vs. Double-Beam Spectrophotometers:

- Single-Beam Instruments: Measure the intensity of light before and after passing through the sample separately. They are simpler and more affordable but require frequent calibration.

- **Double-Beam Instruments:** Split the light beam into two paths—one passing through the sample and the other through a reference. This design compensates for fluctuations in light intensity, improving accuracy and stability.

## **Basic Principles of Quantitative Analysis**

Quantitative analysis is a fundamental aspect of analytical chemistry that focuses on determining the amount or concentration of a substance in a sample. It involves precise measurements, mathematical calculations, and calibration techniques to obtain accurate and reproducible results. The key principles of quantitative analysis include:

### **1. Selection of an Analytical Method**

The choice of the appropriate analytical method depends on factors such as nature of the sample, required sensitivity, accuracy, and instrumentation availability. Common quantitative techniques include titrimetry, gravimetry, spectroscopy, chromatography, and electrochemical analysis.

### **2. Calibration and Standardization**

For accurate results, instruments and reagents must be calibrated against known standards. Calibration curves, based on Beer-Lambert's Law in spectrophotometry or external standards in chromatography, are essential to quantify unknown samples.

### **3. Sensitivity and Detection Limits**

A method must have sufficient sensitivity to detect and measure low concentrations. The limit of detection (LOD) and limit of quantification (LOQ) define the smallest quantity that can be reliably measured.

### **4. Accuracy and Precision**

- Accuracy refers to how close the measured value is to the true value.
- Precision refers to the reproducibility of measurements under identical conditions. Both are evaluated using statistical tools such as standard deviation and confidence intervals.

### **5. Error Minimization**

Errors in quantitative analysis can be systematic (instrumental, methodological, or human errors) or random (uncontrollable variations). Proper calibration, replication, and controlled experimental conditions help minimize these errors.

## 6. Stoichiometric Calculations

Chemical reactions in quantitative analysis follow stoichiometric principles, ensuring the exact mole ratio between reactants and products is used for accurate calculations, as seen in titrations and gravimetric analysis.

## 7. Data Interpretation and Validation

Quantitative results must be statistically validated to ensure reliability. Tests like standard deviation, t-tests, F-tests, and confidence limits assess data consistency and significance.

### **Estimation of Metal Ions from Aqueous Solution**

The estimation of metal ions from an aqueous solution is essential in environmental, industrial, and pharmaceutical analysis. Various techniques are used depending on the metal ion concentration and required sensitivity:

1. Spectrophotometric Methods – Metal ions form-colored complexes with reagents (e.g., EDTA, dithizone) and are analyzed using UV-Visible spectrophotometry based on Beer-Lambert's law.
2. Atomic Absorption Spectroscopy (AAS) – Measures the absorption of light by free metal atoms in a flame or graphite furnace, providing high sensitivity for trace metal analysis.
3. Inductively Coupled Plasma Optical Emission Spectroscopy (ICP-OES) – Detects multiple metal ions simultaneously by analyzing emitted light from excited atoms in a plasma state.
4. Electrochemical Methods – Techniques such as voltammetry and potentiometry estimate metal ion concentrations using electrochemical reactions at electrodes.
5. Titrimetric Methods – Complexometric titrations using EDTA are widely used for metal ion estimation, particularly for calcium, magnesium, and transition metals.

### Geometrical Isomers

Geometrical isomerism occurs in compounds with restricted rotation, such as alkenes and coordination complexes, leading to distinct spatial arrangements of atoms or groups.

1. Cis-Trans Isomerism – Found in alkenes and square-planar or octahedral coordination complexes:
  - Cis-isomer: Identical groups are on the same side (e.g., cis-[Pt(NH<sub>3</sub>)<sub>2</sub>Cl<sub>2</sub>]).
  - Trans-isomer: Identical groups are on opposite sides (e.g., trans-[Pt(NH<sub>3</sub>)<sub>2</sub>Cl<sub>2</sub>]).
2. E-Z Isomerism – A more advanced system used when different substituents are present, based on Cahn-Ingold-Prelog priority rules.

Geometrical isomers have different physical and chemical properties, affecting reactivity, polarity, and biological activity.

### Keto-Enol Tautomerism

Keto-enol tautomerism is a dynamic equilibrium between two structural isomers—keto form (C=O) and enol form (C=C-OH)—where a proton shifts along with electron redistribution.

Key Features:

1. Keto Form – Dominates in most cases due to greater stability (e.g., acetone, CH<sub>3</sub>COCH<sub>3</sub>).
2. Enol Form – Stabilized by hydrogen bonding, conjugation, or aromaticity (e.g., phenol, acetoacetic ester).

Significance:

- Influences reactivity in organic synthesis and biochemical reactions.
- Important in biological systems, such as tautomerism in DNA bases (guanine, thymine).

### Infrared Spectroscopy

#### Principle

Infrared spectroscopy is based on the interaction of infrared radiation with molecules, causing them to undergo vibrational transitions. The absorbed IR radiation corresponds to the specific vibrational frequencies of chemical bonds, which provide a unique molecular fingerprint for compound identification.

The fundamental principles of IR spectroscopy include:

1. Molecular Vibrations – Molecules absorb IR radiation, leading to stretching and bending of bonds.
2. Selection Rules – Only vibrations that result in a change in dipole moment are IR-active.
3. Fingerprint Region – The 4000–400  $\text{cm}^{-1}$  range contains unique absorption bands specific to different functional groups.

#### Choice of Source in IR Spectroscopy

The IR source must provide continuous, stable, and intense radiation over the mid-IR (4000–400  $\text{cm}^{-1}$ ) and far-IR (400–10  $\text{cm}^{-1}$ ) regions. Common IR sources include:

1. Globar Source (Silicon Carbide Rod)
  - Heated electrically to 1300–1500°C, emitting radiation similar to a black body.
  - Suitable for mid-IR (4000–400  $\text{cm}^{-1}$ ) applications.
2. Nernst Glower (Zirconium Oxide and Rare Earth Oxides)
  - Operates at 1200–2200°C, producing high-intensity radiation.
  - Covers a broad IR range, including mid and far-IR.
3. Tungsten-Halogen Lamp
  - Commonly used for near-IR (14000–4000  $\text{cm}^{-1}$ ) spectroscopy.
  - Provides continuous emission but is less efficient for mid and far-IR regions.
4. Mercury Arc Lamp
  - Used in far-IR spectroscopy (below 400  $\text{cm}^{-1}$ ).
  - Emits radiation through an electric discharge in mercury vapor.
5. Carbon Dioxide Laser
  - Provides intense radiation at specific far-IR frequencies.

- Used in high-resolution IR applications and selective molecular studies.

## **1. Monochromator in IR Spectroscopy**

A monochromator is an optical device that selects specific wavelengths from a broad-spectrum IR source before they interact with the sample. It ensures accurate measurement by isolating the desired IR frequencies.

Types of Monochromators:

- Prisms (Lithium Fluoride, Sodium Chloride, Potassium Bromide) – Used in early IR spectrometers but limited by material absorption.
- Diffraction Gratings – Most commonly used; provide high resolution by dispersing light based on wavelength.
- Interferometers (Michelson Interferometer in FTIR) – Used in Fourier Transform Infrared Spectroscopy (FTIR) to process all IR frequencies simultaneously, improving speed and accuracy.

## **2. Detectors in IR Spectroscopy**

Detectors measure the intensity of transmitted or absorbed IR radiation after interaction with the sample.

Types of Detectors:

- Thermal Detectors (Bolometers, Thermocouples, Pyroelectric detectors) – Measure temperature changes due to absorbed IR radiation.
- Photodetectors (Photoconductive & photovoltaic detectors) – Provide faster response times and higher sensitivity, commonly used in FTIR systems.

## **3. Single and Double Beam IR Spectrometers**

- Single Beam IR Spectrometer:
  - Measures the intensity of IR radiation passing through a sample.
  - Requires separate blank (reference) and sample measurements, leading to longer analysis time.
- Double Beam IR Spectrometer:

- Simultaneously measures the sample and reference intensities.
- Improves accuracy by compensating for source fluctuations and environmental factors.

Advantage of Double Beam: Higher precision due to continuous correction of intensity variations.

#### **4. Sampling Techniques in IR Spectroscopy**

The choice of sampling technique depends on the physical state of the sample (solid, liquid, or gas).

##### **A. Solid Samples:**

- KBr Pellet Method – Sample is mixed with potassium bromide (KBr) and pressed into a transparent pellet.
- Mull Technique (Nujol Mull) – Sample is ground with a liquid paraffin (Nujol) and spread between NaCl plates.
- ATR (Attenuated Total Reflectance) – Directly measures solid samples without complex preparation.

##### **B. Liquid Samples:**

- Thin Film Method – A drop of liquid is sandwiched between two NaCl or KBr plates.
- ATR Technique – Liquid samples can also be analyzed directly using ATR without solvent interference.

##### **C. Gas Samples:**

- Gas Cells with NaCl or KBr Windows – Used for volatile compounds; requires a long path length for effective absorption.

## **UNIT-IV**

### **THERMAL AND ELECTRO-ANALYTICAL METHODS OF ANALYSIS**

#### **TGA**

Thermogravimetric Analysis (TGA) is a thermal analysis technique used to measure changes in the mass of a sample as a function of temperature or time under a controlled atmosphere. It is primarily used to study thermal stability, decomposition, oxidation, and moisture content of materials.

#### **Principle of TGA**

The basic principle of TGA involves:

1. **Heating the Sample** – The sample is placed in a small crucible inside a furnace, and its temperature is gradually increased at a controlled rate.
2. **Continuous Mass Measurement** – A highly sensitive balance continuously records the mass of the sample as it undergoes thermal changes.
3. **Controlled Atmosphere** – The analysis is conducted under different gases (e.g., nitrogen, oxygen, or argon) to study decomposition in inert or oxidative conditions.
4. **Mass Loss Interpretation** – The recorded weight loss corresponds to physical or chemical changes like moisture evaporation, decomposition, or oxidation.

#### **Typical TGA Profile**




A TGA curve plots mass (%) vs. temperature ( $^{\circ}\text{C}$ ) and shows distinct weight loss steps, which indicate different thermal events:

- Step 1: Evaporation of water or volatile compounds.
- Step 2: Decomposition of organic materials or polymers.
- Step 3: Oxidation or formation of stable residues (e.g., metal oxides, ash content).


TGA is widely used in material science, polymers, pharmaceuticals, and environmental studies for characterizing thermal stability, composition, and degradation behavior of materials.

### TGA – Instrumentation



A typical TGA system consists of several essential components. The microbalance is a highly sensitive weighing device that continuously measures small mass changes in the sample. The furnace provides controlled heating at a precise rate, ensuring uniform temperature increase. A sample holder is used to place the test material, and an atmosphere control system regulates the gas environment (e.g., inert gases like nitrogen or reactive gases like oxygen) inside the chamber to study oxidation or thermal decomposition reactions. A computer system records and analyzes the data, producing a thermogram that plots weight percentage against temperature.

### Differential Thermal Analysis (DTA) – Principle



Differential Thermal Analysis (DTA) is another thermal analysis technique that measures the temperature difference ( $\Delta T$ ) between a sample and an inert reference material while both are subjected to the same heating program. This method helps identify endothermic (heat absorption) and exothermic (heat release) reactions occurring in the material. Endothermic peaks correspond to processes like melting, dehydration, and phase transitions, whereas exothermic peaks indicate oxidation, crystallization, or decomposition. Unlike TGA, which records weight loss, DTA focuses on heat energy changes within the sample.

### DTA - Instrumentation

The DTA setup includes a furnace for uniform heating of both the sample and reference materials. The sample and reference holders are designed to ensure accurate thermal comparison. Thermocouples are embedded in both holders to measure temperature differences, and a data acquisition system records the generated thermal curves.

### Methods of Obtaining Thermograms

Thermograms are graphical representations of TGA and DTA data, showing how mass or temperature differences change with temperature or time.

- TGA Thermogram: A plot of mass (%) vs. temperature ( $^{\circ}\text{C}$ ). The curve shows weight loss at different temperatures, indicating decomposition steps, moisture loss, or oxidation processes.

- DTA Thermogram: A plot of temperature difference ( $\Delta T$ ) vs. temperature ( $^{\circ}\text{C}$ ). Peaks on the graph correspond to thermal transitions such as melting, crystallization, or decomposition.

### **Factors Affecting TGA/DTA Results**

Several factors influence the accuracy and interpretation of TGA and DTA results.

- Heating rate: A higher heating rate can shift decomposition temperatures and affect reaction kinetics.
- Sample size: A large sample may lead to uneven heating, while too small a sample may provide low signal intensity.
- Atmosphere and gas flow rate: Using an inert gas (e.g., nitrogen) prevents oxidation, whereas oxygen can facilitate combustion reactions.
- Crucible material: The choice of crucible affects thermal conductivity and reaction behavior. Alumina and platinum crucibles are commonly used.

### **Thermal Analysis of Silver Nitrate, Calcium Oxalate, and Calcium Acetate**


TGA and DTA are useful in analyzing the thermal decomposition behavior of various compounds.

- Silver Nitrate ( $\text{AgNO}_3$ ) undergoes decomposition into silver ( $\text{Ag}$ ), nitrogen dioxide ( $\text{NO}_2$ ), and oxygen ( $\text{O}_2$ ) at high temperatures.
- Calcium Oxalate ( $\text{CaC}_2\text{O}_4 \cdot \text{H}_2\text{O}$ ) undergoes stepwise weight loss, first losing water, then converting to calcium carbonate ( $\text{CaCO}_3$ ), and finally decomposing into calcium oxide ( $\text{CaO}$ ).
- Calcium Acetate ( $\text{Ca}(\text{C}_2\text{H}_3\text{O}_2)_2$ ) decomposes into calcium carbonate and later forms  $\text{CaO}$  with  $\text{CO}_2$  evolution.

### **Differential Scanning Calorimetry (DSC) – Principle**

Differential Scanning Calorimetry (DSC) is a technique used to measure heat flow differences between a sample and a reference material as both are subjected to controlled heating. This method is widely applied to study melting points, crystallization, phase transitions, and glass transition temperatures ( $T_g$ ). Unlike DTA, which measures temperature differences, DSC provides quantitative information on heat capacity, enthalpy changes, and reaction kinetics.

### **DSC – Instrumentation**



The DSC system consists of sample and reference pans, where the sample undergoes heating, and the reference remains thermally stable. Heat flow sensors detect exothermic and endothermic reactions, while a temperature-controlled furnace ensures uniform heating. A cooling system is included for low-temperature studies, such as analyzing polymers and biomaterials.

### Applications of DSC

- Determining melting and crystallization temperatures of materials.
- Studying polymeric transitions (glass transition temperature,  $T_g$ ).
- Evaluating thermal stability of pharmaceuticals and drug formulations.
- Measuring specific heat capacity ( $C_p$ ) of substances.

### Electroanalytical Methods: Polarography and Cyclic Voltammetry

#### Polarography – Principle

Polarography is an electroanalytical technique used to study redox reactions of electroactive species in solution. It is based on the measurement of current as a function of applied voltage in an electrochemical cell. The key feature of polarography is the use of a dropping mercury electrode (DME) as the working electrode, which provides a fresh electrode surface with each mercury drop, minimizing surface contamination. As the voltage increases, reduction or oxidation of the analyte occurs at the electrode surface, generating a diffusion-controlled current known as the limiting current ( $I_l$ ). The resulting polarogram (current vs. voltage plot) provides qualitative and quantitative information about the electroactive species.

#### Polarography – Instrumentation

A polarographic system consists of the following components:

1. Dropping Mercury Electrode (DME): The working electrode, where reduction or oxidation of the analyte occurs. Mercury is ideal due to its high hydrogen overpotential and renewable surface.
2. Reference Electrode: Usually a saturated calomel electrode (SCE) or silver/silver chloride (Ag/AgCl) electrode provides a stable reference potential.
3. Auxiliary Electrode: A platinum wire is typically used to complete the circuit.
4. Electrolyte Solution: Contains the analyte and a supporting electrolyte (e.g., KCl) to maintain conductivity.
5. Voltage Source and Function Generator: Applies a linearly varying potential to the working electrode.
6. Current Detector and Recorder: Measures and records the current response to applied voltage, producing a polarogram.

#### Applications of Polarography

- Analysis of metal ions: Used in detecting and quantifying trace levels of heavy metals (e.g.,  $\text{Pb}^{2+}$ ,  $\text{Cd}^{2+}$ ,  $\text{Zn}^{2+}$ ).
- Pharmaceutical analysis: Determines active ingredients in drugs and their degradation products.
- Organic compound analysis: Detects oxygen, peroxides, and functional groups in organic molecules.
- Environmental monitoring: Used for water quality assessment and detecting pollutants in wastewater.

#### Derivative Polarography


Derivative polarography is an advanced modification where the first or second derivative of the polarographic wave is recorded. This improves resolution and sensitivity, making it easier to distinguish between closely spaced redox peaks, particularly in complex mixtures. The first derivative of the current vs. voltage curve enhances peak sharpness, allowing precise determination of half-wave potentials and concentrations.

## Cyclic Voltammetry – Principle

Cyclic Voltammetry (CV) is a powerful electrochemical technique used to study redox properties, reaction kinetics, and electrode processes. In CV, the applied potential is cycled back and forth between two limits while recording the resulting current. This method provides detailed information on electron transfer mechanisms, reversibility of reactions, and diffusion coefficients.

During the forward voltage sweep, an analyte undergoes oxidation or reduction, generating a peak current at its characteristic potential. As the voltage is reversed, the reaction is reversed (e.g., a reduced species is oxidized back), forming a second peak. The shape, position, and intensity of these peaks help characterize the redox behavior of the analyte.

## Cyclic Voltammetry – Instrumentation



1. Working Electrode: A solid electrode (e.g., glassy carbon, platinum, or gold) where redox reactions occur.
2. Reference Electrode: Typically, an Ag/AgCl or SCE electrode provides a stable reference potential.
3. Counter (Auxiliary) Electrode: A platinum or graphite electrode completes the circuit.
4. Potentiostat: Controls the applied voltage and measures the resulting current.
5. Electrolyte Solution: Contains the analyte and supporting electrolyte to enhance conductivity.
6. Data Acquisition System: Records and analyzes the cyclic voltammogram.

## Applications of Cyclic Voltammetry

- Characterization of redox systems: Determines formal redox potentials, reaction reversibility, and electron transfer kinetics.
- Study of electrocatalysts: Evaluates catalytic activity for applications like fuel cells and sensors.
- Organic and inorganic reaction mechanisms: Explores intermediate species in electron transfer reactions.
- Biosensors and drug analysis: Used in pharmaceutical and biochemical research for enzyme and drug interaction studies.

## **UNIT-V**

### **SEPARATION AND PURIFICATION TECHNIQUES**

Separation and purification techniques play a crucial role in scientific research, industrial applications, and pharmaceutical processes. These techniques are essential for isolating pure substances from complex mixtures, removing impurities, and ensuring the quality of chemical compounds. The choice of a suitable technique depends on several factors, including the nature of the sample, the desired purity level, and the specific properties of the components involved.

The classification of separation techniques is based on different principles, including physical, chemical, and physicochemical properties. Physical separation methods involve techniques such as filtration, centrifugation, and distillation, which rely on differences in particle size, density, or boiling points. Chromatographic techniques, including Thin Layer Chromatography (TLC), Gas Chromatography (GC), and High-Performance Liquid Chromatography (HPLC), are widely used for separating complex mixtures based on differential adsorption or partitioning between a stationary and mobile phase. Additionally, electrochemical methods such as electrophoresis and ion-exchange chromatography separate charged molecules based on their movement under an electric field.

The effectiveness of these techniques depends on several key principles. One fundamental principle is phase separation, where components are selectively retained in different phases, as

seen in extraction and chromatography. Another important principle is solubility differences, which govern techniques like crystallization and precipitation, allowing selective removal of impurities. The molecular size and shape of compounds influence separation in techniques such as dialysis and ultrafiltration, while differences in volatility and boiling points form the basis of various distillation methods. Electrical properties, such as charge and potential differences, are critical in electrochemical techniques used for protein purification and DNA separation.

Several factors influence the efficiency of separation and purification. The physical and chemical properties of substances, including solubility, polarity, and volatility, determine the suitability of a particular technique. Temperature and pressure also play a significant role, as some methods require specific conditions to achieve optimal separation, such as vacuum distillation. The choice of solvents or media affects the partitioning of components in extraction and chromatography, and proper selection is crucial for achieving high-purity products. Additionally, parameters like flow rate, pH, and ionic strength can impact the resolution and efficiency of chromatographic and electrochemical techniques.

## **Solvent Extraction: Principle, Process, and Applications**

### **Introduction**

Solvent extraction, also known as liquid-liquid extraction (LLE), is a widely used technique for separating and purifying compounds based on their differential solubility in two immiscible liquids. This method is commonly applied in chemical, pharmaceutical, and metallurgical industries to isolate valuable substances from mixtures.

### **Principle of Solvent Extraction**

The principle of solvent extraction relies on the distribution of a solute between two immiscible liquid phases:

- Aqueous Phase (usually water-based)
- Organic Phase (a non-polar organic solvent such as ether, chloroform, or hexane)

When a mixture containing the target compound is introduced into a two-phase system, the solute selectively partitions between the two phases according to its solubility and affinity for each solvent. The distribution ratio ( $D$ ) is determined by the partition coefficient, which depends on factors such as polarity, temperature, and solvent interactions.

### **Process of Solvent Extraction**



1. **Selection of Solvent:** The organic solvent must be immiscible with water, selectively dissolve the target compound, and be easily removable.
2. **Mixing of Phases:** The mixture is vigorously shaken or stirred to allow the solute to transfer from the aqueous phase into the organic solvent.
3. **Phase Separation:** The two layers are allowed to settle, and the denser phase (aqueous or organic) is separated using a separating funnel.
4. **Solvent Recovery:** The extracted compound is recovered by evaporating or distilling the solvent, leaving behind the purified substance.

### **Factors Affecting Solvent Extraction**

- **Solvent Selection:** The efficiency depends on the polarity and selectivity of the solvent.
- **pH Control:** Adjusting pH can enhance or suppress the ionization of solutes, improving separation.
- **Temperature:** Higher temperatures can affect the solubility and partitioning behavior of compounds.
- **Multiple Extractions:** Performing repeated extractions with fresh solvent increases yield and purity.

### **Applications of Solvent Extraction**

- **Pharmaceutical Industry:** Used for purifying drugs and isolating active ingredients from natural sources.
- **Metal Extraction:** Applied in hydrometallurgy to extract metals like uranium, copper, and rare earth elements.
- **Environmental Science:** Used for removing pollutants, such as organic contaminants, from wastewater.
- **Food Industry:** Extracts flavors, essential oils, and natural pigments from plant materials.

### **Liquid -Liquid Extraction**

#### **Introduction**

Liquid-Liquid Extraction (LLE), also known as solvent extraction, is a separation technique used to transfer a solute from one liquid phase to another. It is widely used in chemical, pharmaceutical, and environmental industries for the purification and isolation of compounds. The process is based on the differential solubility of substances in two immiscible liquids.

#### Principle of Liquid-Liquid Extraction

The principle of LLE relies on the partitioning of a solute between two immiscible liquid phases:

- Aqueous Phase (Polar Solvent) – Typically water or an aqueous solution.
- Organic Phase (Non-Polar Solvent) – A non-polar organic solvent such as chloroform, ether, or hexane.

When the two phases are mixed, the solute distributes itself between them according to its solubility and partition coefficient. The efficiency of extraction is governed by the distribution coefficient ( $K_d$ ), which is the ratio of solute concentration in the organic phase to that in the aqueous phase.

#### Process of Liquid-Liquid Extraction

1. Selection of Solvent – The solvent must be immiscible with water, highly selective for the target compound, and easily removable after extraction.
2. Mixing the Two Phases – The aqueous and organic solvents are mixed to allow the transfer of the solute into the preferred phase.
3. Separation of Phases – The two immiscible liquids are allowed to settle in a separating funnel, where they form distinct layers.
4. Solvent Recovery – The organic phase containing the extracted solute is separated, and the solute is recovered by evaporation, distillation, or re-extraction.

#### Factors Affecting Liquid-Liquid Extraction

- Solvent Selection – The solvent must selectively dissolve the target compound while being immiscible with the aqueous phase.
- pH Adjustment – The ionization state of the solute can be controlled by adjusting pH, enhancing its transfer to the organic phase.
- Temperature – Changes in temperature can affect solubility and distribution ratios.
- Multiple Extractions – Performing multiple extractions with fresh solvent increases efficiency and improves yield.

#### Applications of Liquid-Liquid Extraction

- Pharmaceutical Industry – Used for the extraction of drugs, antibiotics, and active ingredients from plant materials.

- Metal Recovery – Applied in hydrometallurgy to extract metals such as uranium, copper, and rare earth elements.
- Environmental Science – Used for removing organic pollutants, pesticides, and heavy metals from wastewater.
- Food Industry – Extraction of flavors, essential oils, and natural pigments from raw materials.

## **Chromatography: Principles, Types, and Separation Mechanisms**

Chromatography is a powerful analytical technique used for separating, identifying, and quantifying components in a mixture. It plays a crucial role in various scientific disciplines such as chemistry, pharmaceuticals, biotechnology, and environmental science. The fundamental principle of chromatography is the differential migration of sample components through a stationary phase under the influence of a mobile phase. The interaction between the sample, stationary phase, and mobile phase determines the separation efficiency.

### **Principle of Chromatography**

The principle of chromatography is based on the selective distribution of different components of a mixture between two phases:

1. Stationary Phase: A solid or liquid phase that remains fixed within the system.
2. Mobile Phase: A liquid or gas that carries the sample through the stationary phase.

As the sample moves with the mobile phase, its components interact differently with the stationary phase based on adsorption, partition, or ion-exchange properties, leading to their separation. The extent of interaction determines the retention time of each component, allowing for effective separation and analysis.

### **Classification of Chromatography**


Chromatography is broadly classified based on two factors:

1. Based on the Physical State of the Mobile Phase:
  - Liquid Chromatography (LC): Uses a liquid mobile phase.
  - Gas Chromatography (GC): Uses a gaseous mobile phase.
2. Based on the Separation Mechanism:

- Adsorption Chromatography: Separation occurs based on the differential adsorption of sample components onto the stationary phase.
- Partition Chromatography: Components separate based on their differential solubility in the mobile and stationary phases.
- Ion-Exchange Chromatography: Charged molecules interact with oppositely charged groups in the stationary phase.
- Size-Exclusion Chromatography: Molecules are separated based on their size as they pass through a porous stationary phase.
- Affinity Chromatography: Specific interactions between biomolecules (such as antigen-antibody or enzyme-substrate interactions) facilitate separation.

## Types of Chromatography

### 1. Column Chromatography



Column chromatography is a fundamental separation technique where the sample mixture is passed through a column filled with a stationary phase. The separation occurs as different components interact with the stationary phase to varying degrees.


- Choice of Adsorbents: Common adsorbents include silica gel, alumina, and cellulose.
- Solvent Selection: The mobile phase is chosen based on polarity, with common solvents being ethanol, hexane, methanol, and acetone.

- Elution Mechanism: Components elute from the column at different rates depending on their affinity to the stationary phase.

#### **Applications:**

- Purification of chemical compounds.
- Separation of plant extracts and pharmaceutical products.

## **2. Thin-Layer Chromatography (TLC)**




TLC is a simple and rapid technique for separating and identifying compounds in a mixture. It employs a thin layer of stationary phase (silica gel, alumina) coated onto a glass, plastic, or metal plate.

- Process: A small amount of the sample is spotted on the TLC plate, which is placed in a solvent system. The mobile phase travels up the plate via capillary action, separating components based on their interaction with the stationary phase.
- Detection Methods: UV light, iodine vapors, and chemical stains are used to visualize separated compounds.

#### **Applications:**

- Drug analysis.
- Quality control in pharmaceuticals.
- Forensic science.


## **3. Paper Chromatography**



Paper chromatography is a cost-effective method mainly used for qualitative analysis. It involves a strip of filter paper as the stationary phase and a liquid solvent as the mobile phase.

- Separation Principle: Components migrate at different rates due to differences in solubility and interaction with the paper.
- Types: Ascending, descending, and radial chromatography.
- Applications: Identifying amino acids, sugars, and plant pigments.

#### 4. Gas Chromatography (GC)




Gas chromatography is an advanced separation technique for analyzing volatile and thermally stable compounds. It uses a gas mobile phase (carrier gas) to transport analytes through a column.

- Principle: Separation occurs based on boiling points and interaction with the stationary phase.
- Choice of Carrier Gas: Common gases include helium, nitrogen, and hydrogen.
- Detectors Used: Flame Ionization Detector (FID) and Thermal Conductivity Detector (TCD).

#### **Applications:**

- Environmental monitoring (air pollution analysis).
- Drug and food safety analysis.

### **5. High-Performance Liquid Chromatography (HPLC)**



HPLC is a sophisticated chromatographic technique used for high-resolution analysis of complex mixtures. It involves a liquid mobile phase that carries the sample through a packed column under high pressure.

- Types:
  - Normal-Phase HPLC: Uses a polar stationary phase and a non-polar mobile phase.
  - Reverse-Phase HPLC: Uses a non-polar stationary phase and a polar mobile phase.
- Advantages: High sensitivity, accuracy, and faster analysis.

#### **Applications:**

- Pharmaceutical analysis.
- Biotechnology and quality control.

## **6. Electrophoresis**

Electrophoresis is used to separate charged molecules like proteins and nucleic acids based on their movement in an electric field.

- Types: Gel electrophoresis, capillary electrophoresis.
- Applications: DNA sequencing, protein analysis, and forensic investigations.

## **Choice of Adsorbents and Solvents**

- Adsorbents: Selection depends on the polarity and nature of the sample. Common adsorbents include silica gel, alumina, and cellulose.
- Solvents: The choice of solvent affects separation efficiency. Non-polar solvents like hexane are used for non-polar compounds, while polar solvents like ethanol or methanol are used for polar compounds.

## **Preparation of Column**

- Packing: The stationary phase is packed into a column, either by dry packing or wet packing.
- Sample Introduction: The sample is applied at the top of the column before allowing the mobile phase to pass through.
- Elution: Components elute at different rates based on interaction with the stationary phase.

## **Elution Mechanism of Separation**

### **1. Adsorption Chromatography**

- The sample components adhere to the surface of the stationary phase.
- Used in TLC and column chromatography.

### **2. Partition Chromatography**

- Separation occurs based on differential solubility between the mobile and stationary phases.
- Used in paper chromatography and liquid-liquid extraction.

### **3. Ion-Exchange Chromatography**

- Ions in the sample exchange with oppositely charged ions in the stationary phase.
- Used in water purification and protein separation.



## Development of Chromatograms and Rf Value

Chromatography is a technique used to separate components of a mixture based on their interaction with the stationary and mobile phases. Once the separation occurs, the result is recorded as a chromatogram, which visually represents the movement of different components. The Rf value (Retention factor) is a crucial parameter used in Thin Layer Chromatography (TLC) and Paper Chromatography to quantify the separation efficiency.

### Development of Chromatograms

The development of a chromatogram involves allowing the mobile phase (solvent) to move through the stationary phase, carrying the sample components at different rates. The process consists of the following steps:

1. **Sample Application:** A small amount of the sample mixture is spotted onto the stationary phase (TLC plate or chromatography paper).
2. **Solvent Selection:** A suitable solvent or mixture of solvents is chosen based on the nature of the sample.
3. **Chromatogram Development:** The plate or paper is placed in a sealed chamber containing the mobile phase. The solvent rises through capillary action, separating the components.
4. **Detection:** After the solvent front reaches an appropriate height, the chromatogram is dried, and the separated spots are visualized using UV light, iodine staining, or chemical reagents.

The chromatogram provides qualitative and quantitative information about the sample, including the number of components, their interaction with the stationary phase, and their polarity.

### Retention Factor (Rf Value)

The Rf value is a numerical representation of how far a compound travels relative to the solvent front. It is calculated using the formula:

$$R_f = \frac{\text{Distance traveled by the compound}}{\text{Distance traveled by the solvent front}}$$

$$R_f = \frac{\text{Distance travelled by the compound}}{\text{Distance travelled by the solvent front}}$$

Key Points About Rf Value:

- The Rf value ranges between 0 and 1.

- A higher R<sub>f</sub> value indicates lower interaction with the stationary phase and higher solubility in the mobile phase.
- A lower R<sub>f</sub> value suggests stronger binding to the stationary phase and less movement with the solvent.
- The R<sub>f</sub> value helps in identifying compounds by comparing them with reference standards.

#### **Factors Affecting R<sub>f</sub> Value:**

1. Nature of the Compound: Polar compounds interact more with the stationary phase, leading to lower R<sub>f</sub> values, while non-polar compounds travel further.
2. Type of Stationary Phase: The composition of the stationary phase (e.g., silica gel, cellulose) affects adsorption and separation.
3. Mobile Phase Composition: The choice of solvent influences the movement of analytes. A more polar solvent can increase the R<sub>f</sub> value of polar compounds.
4. Temperature and Humidity: Variations in temperature and humidity can alter solvent flow and affect R<sub>f</sub> values.
5. Thickness of the Stationary Phase: A thicker layer may cause stronger adsorption, reducing R<sub>f</sub> values.

#### **Significance of R<sub>f</sub> Value and Chromatograms:**

- Used for qualitative analysis in forensic science, pharmaceuticals, and biochemical studies.
- Helps in identifying unknown compounds by comparing with reference substances.
- Assists in monitoring chemical reactions and purity analysis.
- Used in food quality testing and plant compound analysis.